

The background of the entire page is a dark, artistic photograph of a desk. On the desk, there are two large white speakers, a black keyboard, a white mug, a vintage-style rotary telephone, and several small, whimsical figurines. The lighting is moody, with highlights on the desk surfaces. The logo 'CREATIVEPRESETS' is centered at the top, with 'CREATIVE' in white and 'PRESETS' in yellow, enclosed in a thin yellow rectangular border.

# CREATIVEPRESETS

SHOOT / PROCESS / REPEAT

## How to Use Lighting Overlays

Place the texture/overlay over your photo.

Change the blend mode to suit your needs (we suggest MULTIPLY, OVERLAY or SOFT LIGHT).

Use a layer mask to non-destructively brush off any portion of the texture/overlay that you'd like to remove.

# CREATIVEPRESETS

SHOOT / PROCESS / REPEAT

## How to install Brushes in Lightroom 4, 5, 6, and Lightroom CC

### Macintosh / Windows

1. Unzip your download and open the 'Creative Presets Brushes' folder.
2. Copy all the .lrtemplate files from that folder so you can paste them later.
3. Open Lightroom and go to your preferences by clicking Lightroom in the top left and then "Preferences."
4. In the Preferences window, click the 'Presets' tab at the top.
5. Under 'Location' click the 'Show Lightroom Presets Folder' button.
6. A Finder window will pop up. Open the 'Lightroom' folder, and then the 'Local Adjustment Presets' folder.
7. Paste your Lightroom Creative Presets files into this folder. <http://www.creativepresets.com>
8. Quit and relaunch Lightroom.
9. You will find your brushes under the "Adjustment Brushes" section. The icon looks like a brush/slider and can be found in the top right hand corner of your editing panel in the Develop module. You can also quickly get to the brushes by pressing 'K'.
10. If you see a lightning bolt symbol next to your histogram in the top right of the develop module, be sure to update your profile settings by clicking on it and following the prompts. If you don't, the brushes won't work properly!

## How to install ACR presets in Photoshop Adobe Camera Raw

- 1.. First, after your purchase, download and unzip the file to your computer.
- 2.. Navigate to the folder where the presets are saved:

### Macintosh

Username/Library/Application Support/Adobe/Camera Raw/Settings

(If you don't see the Library folder, do the following: Open up the Terminal application on your computer, and enter the following text: `chflags nohidden ~/Library/`, then click the Return key).

### Windows

C:\Users\[User Name]\AppData\Roaming\Adobe\CameraRaw\Settings or  
Username/AppData/Roaming/Adobe/CameraRaw/Settings.

(If you don't see that location, then you'll need to make sure that your "Show Hidden Files..." setting is turned on. To do this, go to the Control Panel > Appearance and Personalization > Folder Options > Show Hidden Files and Folders. Then, in the the View tab, change the default setting of "Don't Show Hidden Files, Folders and Drives" to "Show Hidden Files, Folders, and Drives" then click the OK button.)

3. Once you have this folder opened, locate the download folder with the presets and open this folder in a separate window. Then, drag the .xmp files over to the Settings folder. (You need to be sure that you DO NOT add additional folders to the settings folder; ACR does not support sub-folders.) Here's what your folder will look like when you're done:

4. Now, open up an image into Adobe Camera Raw (close and re-open it if you already had it opened). Click on the "Presets" tab near the top-right and your presets will be added to the list: